


```
LL      IIIIII  BBBB BBBB  EEEEEEEEE  DDDDDDDDD  IIIIII  VV      VV
LL      IIIIII  BBBB BBBB  EEEEEEEEE  DDDDDDDDD  IIIIII  VV      VV
LL      II      BBBB      BB  EE          DD      DD  II      VV      VV
LL      II      BBBB      BB  EE          DD      DD  II      VV      VV
LL      II      BBBB      BB  EE          DD      DD  II      VV      VV
LL      II      BBBB      BB  EE          DD      DD  II      VV      VV
LL      II      BBBB      BB  EE          DD      DD  II      VV      VV
LL      II      BBBB      BB  EE          DD      DD  II      VV      VV
LL      II      BBBB      BB  EE          DD      DD  II      VV      VV
LL      II      BBBB      BB  EE          DD      DD  II      VV      VV
LL      II      BBBB      BB  EE          DD      DD  II      VV      VV
LLLLLLLLLLLL  IIIIII  BBBB BBBB  EEEEEEEEE  DDDDDDDDD  IIIIII  VV      VV
LLLLLLLLLLLL  IIIIII  BBBB BBBB  EEEEEEEEE  DDDDDDDDD  IIIIII  VV      VV
```

```
LL      IIIIII  SSSSSSSS
LL      IIIIII  SSSSSSSS
LL      II      SS
LL      II      SS
LL      II      SS
LL      II      SS
LL      II      SSSSSS
LL      II      SSSSSS
LL      II      SS
LL      II      SS
LL      II      SS
LLLLLLLLLLLL  IIIIII  SSSSSSSS
LLLLLLLLLLLL  IIIIII  SSSSSSSS
```


LIB\$EDIV
Table of contents

- Execute EDIV instruction

I 2

15-SEP-1984 23:59:10 VAX/VMS Macro V04-00

Page 0

(2) 46
(3) 76

DECLARATIONS
LIB\$EDIV - Execute EDIV instruction

```
0000 1      .TITLE  LIB$EDIV - Execute EDIV instruction
0000 2      .IDENT  /1-001/                          ; File: LIBEDIV.MAR Edit: SBL1001
0000 3
0000 4
0000 5 *****
0000 6 *
0000 7 *  COPYRIGHT (c) 1978, 1980, 1982, 1984 BY
0000 8 *  DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.
0000 9 *  ALL RIGHTS RESERVED.
0000 10 *
0000 11 *  THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED
0000 12 *  ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE
0000 13 *  INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER
0000 14 *  COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY
0000 15 *  OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY
0000 16 *  TRANSFERRED.
0000 17 *
0000 18 *  THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE
0000 19 *  AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT
0000 20 *  CORPORATION.
0000 21 *
0000 22 *  DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS
0000 23 *  SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.
0000 24 *
0000 25 *
0000 26 *****
0000 27
0000 28
0000 29 ++
0000 30 : FACILITY: General Utility Library
0000 31
0000 32 : ABSTRACT:
0000 33 :
0000 34 :     This module contains LIB$EDIV, which makes the VAX EDIV instruction
0000 35 :     available as a callable procedure.
0000 36 :
0000 37 : ENVIRONMENT: Runs at any access mode, AST Reentrant
0000 38 :
0000 39 : AUTHOR: Steven B. Lionel, CREATION DATE: 8-July-1981
0000 40 :
0000 41 : MODIFIED BY:
0000 42 :
0000 43 : 1-001 - Original. SBL 8-July-1981
0000 44 :--
```



```
0000 46 .SBTTL DECLARATIONS
0000 47 :
0000 48 : LIBRARY MACRO CALLS:
0000 49 :
0000 50 $SSDEF ; Define SS$ symbols
0000 51 $CHFDEF ; Define CHF$ symbols
0000 52 :
0000 53 : EXTERNAL DECLARATIONS:
0000 54 :
0000 55 .DSABL GBL ; Force all external symbols to be declared
0000 56 .EXTRN LIB$SIG_TO_RET ; Convert signal to return with status
0000 57 :
0000 58 : MACROS:
0000 59 :
0000 60 : NONE
0000 61 :
0000 62 : EQUATED SYMBOLS:
0000 63 :
0000 64 : NONE
0000 65 :
0000 66 : OWN STORAGE:
0000 67 :
0000 68 : NONE
0000 69 :
0000 70 : PSECT DECLARATIONS:
0000 71 :
00000000 72 .PSECT _LIB$CODE PIC, USR, CON, REL, LCL, SHR, -
0000 73 EXE, RD, NOWRT, LONG
0000 74
```

```
0000 76 .SBTTL LIB$EDIV - Execute EDIV instruction
0000 77 :++
0000 78 : FUNCTIONAL DESCRIPTION:
0000 79 :
0000 80 : This procedure makes the VAX EDIV instruction available as
0000 81 : a callable procedure.
0000 82 :
0000 83 : The dividend argument is divided by the divisor argument;
0000 84 : the quotient argument is replaced by the quotient and the
0000 85 : remainder argument is replaced by the remainder.
0000 86 :
0000 87 : For more information, see the VAX-11 Architecture Handbook.
0000 88 :
0000 89 : CALLING SEQUENCE:
0000 90 :
0000 91 : status.wlc.v = LIB$EDIV (divisor.rl.r, dividend.rq.r,
0000 92 : quotient.wl.r, remainder.wl.r)
0000 93 :
0000 94 : FORMAL PARAMETERS:
0000 95 :
00000004 0000 96 : divisor = 4 ; The address of the longword integer divisor.
00000008 0000 97 :
00000008 0000 98 : dividend = 8 ; The address of the quadword integer dividend.
0000000C 0000 99 :
0000000C 0000 100 : quotient = 12 ; The address of the longword integer location
0000 101 : where the quotient will be stored.
00000010 0000 102 :
00000010 0000 103 : remainder = 16 ; The address of the longword integer location
0000 104 : where the remainder will be stored.
0000 105 :
0000 106 : IMPLICIT INPUTS:
0000 107 :
0000 108 : NONE
0000 109 :
0000 110 : IMPLICIT OUTPUTS:
0000 111 :
0000 112 : NONE
0000 113 :
0000 114 : COMPLETION STATUS:
0000 115 :
0000 116 : $$$_NORMAL, normal successful completion
0000 117 : $$$_INTOVF, integer overflow
0000 118 : $$$_INTDIV, integer divide by zero
0000 119 :
0000 120 : SIDE EFFECTS:
0000 121 :
0000 122 : If integer overflow or divide-by-zero occur, then the quotient
0000 123 : operand is replaced by bits 31:0 of the dividend operand, and the
0000 124 : remainder is replaced by zero.
0000 125 :
0000 126 :--
0000 127 :
0000 128 : .ENTRY LIB$EDIV, ^M<IV> ; Entry point
0002 129 : ; IV must be enabled
0002 130 :
0002 131 : MOVAB B^HANDLER, (FP) ; Enable local condition handler
0006 132 : ; to intercept exceptions
```


LIB\$EDIV
1-001

- Execute EDIV instruction
LIB\$EDIV - Execute EDIV instruction

M 2

15-SEP-1984 23:59:10 VAX/VMS Macro V04-00
6-SEP-1984 11:06:01 [LIBRTL.SRC]LIBEDIV.MAR;1

Page 4
(3)

10 BC	0C BC	08 BC	04 BC	7B	0006	133			
					0006	134	EDIV	@divisor(AP), @dividend(AP), -	
					000F	135		@quotient(AP), @remainder(AP)	
					000F	136			
					000F	137	;	+	
					000F	138	:	;	If the EDIV caused an exception, HANDLER will unwind to our caller
					000F	139	:	;	with the correct status.
					000F	140	:	;	-
					000F	141			
50	01	D0			000F	142	MOVL	#SS\$_NORMAL, R0	; Successful completion
		04			0012	143	RET		

```
0013 145 ;+
0013 146 ; Local condition handler to return $$$_INTOVF and $$$_INTDIV as return
0013 147 ; statuses, all other exceptions resignal.
0013 148 ; -
0013 149
0013 150 HANDLER:
0013 151 .WORD ^M<> ; Entry mask
0015 152
50 08 AC D0 0015 153 MOVL CHF$_MCHARGLIST(AP), R0 ; Get mechanism args list address
08 A0 D5 0019 154 TSTL CHF$_MCH_DEPTH(R0) ; Is signal depth zero?
1F 12 001C 155 BNEQ 90$ ; If not, resignal
50 04 AC D0 001E 156 MOVL CHF$_SIGARGLIST(AP), R0 ; Get signal args list address
0000047C 8F 04 A0 D1 0022 157 CMPL CHF$_SIG_NAME(R0), #$$$_INTOVF
002A 158 ; Is it integer overflow?
0A 13 002A 159 BEQL 10$ ; If so, return with status
00000484 8F 04 A0 D1 002C 160 CMPL CHF$_SIG_NAME(R0), #$$$_INTDIV
0034 161 ; Is it integer divide-by-zero?
07 12 0034 162 BNEQ 90$ ; If not, resignal
00000000'GF 07 6C FA 0036 163 10$: CALLG (AP), G^LIB$SIG_TO_RET ; Return to our establisher's caller
; with condition code in R0
50 00000918 8F D0 003D 164 90$: MOVL #$$$_RESIGNAL, R0 ; Resignal (ignored if we just called
0044 166 ; LIB$SIG_TO_RET)
04 0044 167 RET
0045 168
0045 169 .END ; End of module LIB$EDIV
```


LIB\$EDIV
Symbol table

- Execute EDIV instruction

B 3

15-SEP-1984 23:59:10
6-SEP-1984 11:06:01VAX/VMS Macro V04-00
[LIBRTL.SRC]LIBEDIV.MAR;1Page 6
(4)

CHFSL_MCHARGLST	=	00000008		
CHFSL_MCH_DEPTH	=	00000008		
CHFSL_SIGARGLST	=	00000004		
CHFSL_SIG_NAME	=	00000004		
DIVIDEND	=	00000008		
DIVISOR	=	00000004		
HANDLER		00000013	R	02
LIB\$EDIV		00000000	RG	02
LIB\$SIG_TO_RET		*****	X	00
QUOTIENT	=	0000000C		
REMAINDER	=	00000010		
SS\$_INTDIV	=	00000484		
SS\$_INTOVF	=	0000047C		
SS\$_NORMAL	=	00000001		
SS\$_RESIGNAL	=	00000918		

+-----+
! Psect synopsis !
+-----+

PSECT name	Allocation	PSECT No.	Attributes														
. ABS .	00000000 (0.)	00 (0.)	NOPIC	USR	CON	ABS	LCL	NOSHR	NOEXE	NORD	NOWRT	NOVEC	BYTE				
\$ABSS	00000000 (0.)	01 (1.)	NOPIC	USR	CON	ABS	LCL	NOSHR	EXE	RD	WRT	NOVEC	BYTE				
_LIB\$CODE	00000045 (69.)	02 (2.)	PIC	USR	CON	REL	LCL	SHR	EXE	RD	NOWRT	NOVEC	LONG				

+-----+
! Performance indicators !
+-----+

Phase	Page faults	CPU Time	Elapsed Time
Initialization	29	00:00:00.05	00:00:01.47
Command processing	102	00:00:00.33	00:00:03.36
Pass 1	183	00:00:02.66	00:00:11.66
Symbol table sort	0	00:00:00.41	00:00:01.71
Pass 2	44	00:00:00.53	00:00:04.30
Symbol table output	4	00:00:00.02	00:00:00.02
Psect synopsis output	2	00:00:00.02	00:00:00.02
Cross-reference output	0	00:00:00.00	00:00:00.00
Assembler run totals	366	00:00:04.02	00:00:22.54

The working set limit was 1200 pages.
21140 bytes (42 pages) of virtual memory were used to buffer the intermediate code.
There were 30 pages of symbol table space allocated to hold 427 non-local and 2 local symbols.
169 source lines were read in Pass 1, producing 13 object records in Pass 2.
9 pages of virtual memory were used to define 8 macros.

+-----+
! Macro library statistics !
+-----+

Macro library name	Macros defined
_\$255\$DUA28:[SYSLIB]STARLET.MLB;2	5

486 GETS were required to define 5 macros.

LIB\$EDIV
VAX-11 Macro Run Statistics

- Execute EDIV instruction

C 3

15-SEP-1984 23:59:10
6-SEP-1984 11:06:01

VAX/VMS Macro V04-00
[LIBRTL.SRC]LIBEDIV.MAR;1

Page 7
(4)

**F

There were no errors, warnings or information messages.

MACRO/ENABLE=SUPPRESSION/DISABLE=(GLOBAL,TRACEBACK)/LIS=LIS\$:LIBEDIV/OBJ=OBJ\$:LIBEDIV MSRC\$:LIBEDIV/UPDATE=(ENH\$:LIBEDIV)

0206 AH-BT13A-SE
VAX/VMS V4.0

DIGITAL EQUIPMENT CORPORATION
CONFIDENTIAL AND PROPRIETARY

